

# Intel® Distribution for GDB\* Reference Sheet

## Prerequisites

Set your oneAPI environment variables:

```
$ source <ONEAPI_ROOT>/setvars.sh
```

Check if the Debug Companion Driver (DCD) is installed:

```
$ modinfo igfxdcd
```

Install and load DCD if necessary:

```
$ sudo dpkg -i <ONEAPI_ROOT>/debugger/latest/\
igfxdcd-*-Linux.deb
```

```
$ sudo modprobe igfxdcd
```

```
# Or
```

```
$ sudo dpkg -i <ONEAPI_ROOT>/debugger/latest/\
igfxdcd-*-Linux.rpm
```

```
$ sudo modprobe igfxdcd
```

Finally, check that your user is in the `video` (or, in some distributions, `render`) group.

## Auto-Attach

Turn the auto-attach feature off, if desired (e.g. if debugging on CPU or FPGA-emu):

```
$ export INTELGT_AUTO_ATTACH_DISABLE=1
```

Turn the feature on:

```
$ unset INTELGT_AUTO_ATTACH_DISABLE
```

## Useful GDB Commands

**help <cmd>**

Print help info about the command `cmd`.

**run [arg1, ... argN]**

Start the program, optionally with arguments.

**break <filename>:<line>**

Define a breakpoint at given source file's specified line.

**info break**

Show the defined breakpoints.

**delete <N>**

Remove the Nth breakpoint.

**watch <exp>**

Stop when value of the expression `exp` changes.

**step, next**

Single-step a source line, stepping into/over func calls.

**continue**

Continue execution.

**print <exp>**

Print value of expression `exp`.

**backtrace**

Show the function call stack.

**up, down**

Go one level up/down in the function call stack.

**disassemble**

Disassemble the current function.

**info args/locals**

Show the arguments/local vars of the current function.

**info reg <regname>**

Show contents of the specified register.

## Useful GDB Commands (cont'd)

**info inferiors**

Display information about the *inferiors*. For GPU off-loading, one inferior represents the host process, and another (`gdbserver-gt`) represents the kernel.

**info threads <ID>**

Display information about threads with id `ID`, including their active SIMD lanes. Omit `id` to display all threads.

**thread <thread\_id>:<lane>**

Switch context to the SIMD lane `lane` of the specified thread. E.g: `thread 2.6:4`

**thread apply <thread\_id>:<lane> <cmd>**

Apply command `cmd` to the specified lane of the thread. E.g: `'thread apply 2.3:* print element'` prints `element` for each active lane of thread 2.3. Useful for inspecting vectorized values.

**x /<format> <addr>**

Examine the memory at address `addr` according to `format`. E.g: `'x /i $pc'` shows the instruction pointed by the program counter. `'x /8wd &count'` shows 8 words in decimal format located at the address of `count`.

**set nonstop on/off**

Enable/disable the nonstop mode. This command may *not* be used after the program has started.

**set scheduler-locking on/step/off**

Lock the thread scheduler. Useful to keep the other threads stopped while the current thread is stepping (if set to `step`) or resumed (if `on`) to avoid interference.

**maint jit dump <addr> <filename>**

Save the JIT'ed objfile that contains address `addr` into the file `filename`. Useful for extracting the DPC++ kernel when running on the CPU device.

**cond [-force] <N> <exp>**

Define the expression `exp` as the condition for breakpoint `N`. Use the optional `-force` flag to force the condition to be defined even when `exp` is invalid for the current locations of the breakpoint. Useful for defining conditions on breakpoints in JIT-produced code.

## Troubleshooting

**Q:** I see the “`intelgt: gdbserver-gt failed to start.`” error.

⇒ Go over the “Prerequisites” steps. If not interested in GPU debugging, turn off the auto-attach feature.

## Links

[Get Started Guide](#) 

[Release Notes](#) 

[Intel oneAPI Toolkit Forums](#) 

[Intel oneAPI Data Parallel C++ Support](#) 

\* Intel is a trademark of Intel Corporation or its subsidiaries. Other names and brands may be claimed as the property of others.